

# SelectDirect Samgods 1.2 Documentation

Jonas Andersson

**Trafikverket**

Trafikverket, Box 388, 831 25 Östersund. Besöksadress: Kyrkgatan 43 B.

Telefon: 0771-921 921, Texttelefon: 010-123 99 97

Dokumenttitel: SelectDirect Samgods 1.2

Författare: Jonas Andersson

Dokumentdatum: 2019-01-11

Kontaktperson: Petter Hill, PLep

# Content

|   |    |
|---|----|
| <b>SelectDirect Documentation</b> .....         | 4  |
| What does it do? .....                          | 4  |
| Main purpose, selected transport flows .....    | 4  |
| Auxiliary functions.....                        | 5  |
| <b>Program control</b> .....                    | 5  |
| Command line.....                               | 5  |
| Control file.....                               | 5  |
| <b>Program structure</b> .....                  | 8  |
| Main classes .....                              | 8  |
| Utility classes .....                           | 8  |
| <b>Changes in SelectDirect 1.2</b> .....        | 9  |
| New features .....                              | 9  |
| Changes in functionality.....                   | 9  |
| Enhancements .....                              | 9  |
| <b>References</b> .....                         | 9  |
| <b>Appendix – Output data description</b> ..... | 10 |
| LinksSumSL.dat.....                             | 10 |
| ConSumSL.dat .....                              | 10 |
| ChainsSL.dat .....                              | 11 |
| ConnectionsSL.dat.....                          | 12 |
| TotalFlows.dat .....                            | 13 |

# SelectDirect Documentation

SelectDirect.jar is a Java program that performs select link analysis.

## What does it do?

SelectDirect uses spanning tree data to resolve transport flows to link and node level for various purposes. It also carries out some auxiliary tasks of aggregating traffic flows, and preparing files for further use in the Samgods model.

## Main purpose, selected transport flows

The main purpose of SelectDirect is to generate input data for visualization of selected transport flows. For this analysis the program generates five output files. Each contains flows that fulfil the selection criteria given in the program control file.

- LINKSFILE (LinksSumSL.dat) - Total flow per link and vehicle type.
- CONSUMFILE (ConSumSL.dat) - Total flow per connection and vehicle type.
- CHAINSFILE (ChainsSL.dat) - Flow per each transport chain.
- CONNECTIONSFILE (ConnectionsSL.dat) - Flow and distance for each connection in each transport chain.
- TotalFlows.dat Total flow per vehicle type.

Two different types of criteria can be used:

- Select link analysis: Transports that pass certain nodes or links.
- Select zone analysis: Transports that begins in a selected interval of zones and end in another selected interval of zones.

For the first case links and / or nodes are given by keywords LINKSSL and NODESSL. If neither of these keywords are used, all transport chains for the selected commodities will be included. Output include transports that pass given by Selection can include any or all of the given nodes and links and can be required to be passed either in the order given in the keywords or in random order. These visit conditions are defined by the keywords VISITNODE and VISITLINK.

For the second case start zones are given by keyword OZONE, and end zones by DZONE.

## Auxiliary functions

### **Traversal matrices**

Using this option the program can produce so called traversal matrices, files specifying flows to and from the Swedish border zones.

### **GIS data**

This option produces a file Stan.txt that contains flows for each link and Stan group as well as number of trains and used capacity for capacitated rail links.

### **Domestic ratio**

For this option SelectDirect loops over all time and cost LOS matrices, and uses the resolved path together with time and cost data per link to produce new LOS matrices containing the domestic part of time and cost, respectively.

### **Compact Spanning Tree files**

This option produces Spanning Tree files on a compact format, reducing the required storage space with approximately 90%.

### **Cost for empty vehicles**

This function uses LOS data and vehicle cost data to produce a cost file for empty vehicles.

### **CBA sum file**

Generates a file containing the total cost for all transports divided into the categories Domestic, Import, Export, and Transit transports. Also sums the total vehicle kms for these categories.

## **Program control**

### Command line

SelectDirect is a Java command line program. It is run by a command similar to:

```
java -d64 -Xmx4g -Xms2024m -jar SelectDirect.JAR SelectDirect.ct1 slnk
```

### **Command line parameters:**

The task that the program is expected to carry out is defined by a command line argument.

To run a select link analysis use argument **slnk** or leave out as this is the default action.

### Control file

The last part of the command, SelectDirect.ct1, is the name of the control file containing a number of parameters for the program run. These are described below. The control file can contain comments. Those are rows starting with a hyphen ( - ).

### **Control file parameters** *(examples in italic):*

Required parameters are marked with black text.

Optional parameters are marked with blue text.

| <b>Parameters (with example values)</b>                       | <b>Description</b>  |
|---|---|
| <i>ASEKLOS=Input_CBA\LOS</i>                                  | Filepath for ASEK LOS-matrices.   |
| <i>CBASUMFILE=RCM\Output\CBA_aggr.txt</i>                     | Filepath for CBA summary output file.   |
| <i>CAPLINKS=RCM\RailLinkCapacitiesBidirectional_STD.DAT</i>   | List of links with Emme/Voyager numbering system and bidirectional capacity per day.  |
| <i>CCFILES=ChainChoi\OUTPUT\ChainChoi[v]XTD.out</i>           | Filepath for ChainChoiXTD files.  |
| <i>CHAINSFILE=RCM\OUTPUT\ChainsSL.dat</i>                     | Filepath for ChainsSL output files.   |
| <i>COMMODITISSL=1,2,3</i>                                     | All commodities from default value of "MAX_CMD" is checked. In Samgods 1.2 this value is 16.  |
| <i>CONNECTIONSFILE=RCM\OUTPUT\ConnectionsSL.dat</i>           | Filepath for ConnectionsSL files.   |
| <i>CONSUMFILE=RCM\OUTPUT\ConCumSL.dat</i>                     | Filepath for output file for CONSUM.  |
| <i>COSTFILES=ChainChoi\Output\ChainChoi01data07XTD.out</i>    | Filepath for cost files to use.   |
| <i>DFR=200</i>  | Day factor rail.  |
| <i>DZONE</i>  | Destination zone.   |
| <i>EMPTYCOST=RCM\Output\EmptyCost.dat</i>                     | Filepath to EmptyCost output file.  |
| <i>EMPTYFRAC=Extract\emptyfrac.dat</i>                        | Filepath to emptyfraction file.   |
| <i>ERRORLOG=RCM\Error.log</i>                                 | Errors are logged to this file. If the ERRORLOG parameter is omitted the file is called Error.log and placed in the folder specified by the PATH parameter. If the keyword ERRORLOG is used the log is rewritten at the beginning of the J step.                |
| <i>IO_LOG=RCM\UTI_CBA.log</i>                                 | The line IO_LOG=RCM\IOLog_LP[i].log in the ctl file will cause all names of input and output files to be written to file, together with ctl settings.   |
| <i>LINKLIST=RCM\Links_List.txt</i>                            | Input- list of links in the network with ID link followed by Voyager from and to nodes and Emme from and to nodes respectively. Blank or comma separated.   |
| <i>LINKSFILE=RCM\OUTPUT\LinksSumSL.dat</i>                    | Filepath for LinksSumSL output file.  |
| <i>LINKSSL=550700-550652</i>                                  | Comma separated list with links to check. May also include a span (for example 333111-333222).  |
| <i>LINKTIMECOST=RCM\Exported_network_BS2012.txt</i>           | Filepath for exported network.  |
| <i>LOCKS=STD</i><br><i>LOCKS=RCM\LockedSTDLogMod_Soln.txt</i> | LOCKS parameter can take two types of values, either a filename, or the value STD. If the value is STD, locked chains are read from the STDLogMod output files LockedXX.log in folder ChainChoi\OUTPUT. The parameter is mandatory if locked flows are present. |
| <i>LOSPATH=Input\LOS</i>                                      | Filepath for LOS-matrices.  |
| <i>MAX_ARRPATHSIZE=2000</i>                                   | Sets the maximum size of the best-path array. Default value is 2000.  |
| <i>MAX_CAPLINKS=1000</i>                                      | Number of rows from CAPLINKS file. Default 1000. Used by the class SpanningTree.  |
| <i>MAX_CMD=16</i>   | Sets the highest commodity number. Default 16.  |

|   |   |
|---|---|
| <i>MAX_EMMESPAN=300000</i>                                    | Maximum size of the span of Emme zones. Default 300 000 (700000 – 999999). Used by the class SpanningTree.  |
| <i>MAX_INTLINKNO=150000</i>                                   | Maximum internal link number in LINKLIST file. Default 150 000. Used by the class SpanningTree.   |
| <i>MAX_JKEYS=500000</i>                                       | Maximum number of Superindexes in the JLIST file per commodity. Default 500 000. Used in the methods Write_CG_LP_Itr0 and Write_CG_LP_ItrX. If either of these methods fail with an ArrayIndexOutOfBounds error increasing this parameter may fix the problem.                  |
| <i>MAX_POSSOLS=1500000</i>                                    | Maximum number of positive solutions in the Linear Programming output. Used when writing LPX files in iterations 1 or higher. Default 1 500 000. If the program fails with a message of ArrayIndexOutOfBounds in method WriteLPX increasing this parameter may fix the problem. |
| <i>MAX_SPANNODE=2000</i>                                      | Span of nodes in Spanning Tree. Default 2000. Used by the class SpanningTree.   |
| <i>MAX_VOYNODE=50000</i>                                      | Maximum Voyager node number in the NODESLIST file. Default 50 000. Used by the class SpanningTree.  |
| <i>NODESLIST=RCM\Nodes_List.txt</i>                           | Input- List of nodes in the network with Emme and Voyager numbers. Blank or comma separated.  |
| <i>NODESSL=321724,321725</i>                                  | Comma separated list containing border nodes.   |
| <i>OZONE</i>  | Origin zone.  |
| <i>PATH=C:\workfolder</i>                                     | Filepath for default working directory.   |
| <i>SELECTCOMBINE=3</i>  | 1-4. 1 = keepnode. 2 = keeplink. 3 = keepnode OR keeplink. 4 = keepnode AND keeplink.   |
| <i>SL_EMPTY=EXTRACT\OUTPUT\OD_Emp[fj]_FIN.314</i>             | Filepath for OD empty files.  |
| <i>SLCTLINKNETFILE=RCM\OUTPUT&gt;SelectLink_Netw_Flow.dat</i> | Filepath for output file of link network flows.   |
| <i>SLCTLINKSUMMARY=RCM\OUTPUT\Link_TonLoadEmp.dat</i>         | Filepath for output file of link summary by ton, loaded, empties.   |
| <i>SPT_AIR=RCM\PathTreeAir.cmp</i>                            | Path to spanningtree for Air.   |
| <i>SPT_RAIL=RCM\PathTreeRail.cmp</i>                          | Path to spanningtree for Rail.  |
| <i>SPT_ROAD=RCM\PathTreeRoad.cmp</i>                          | Path to spanningtree for Road.  |
| <i>SPT_SEA=RCM\PathTreeSea.cmp</i>                            | Path to spanningtree for Sea.   |
| <i>STANFILE=RCM\Output\COMMODITY_NETWORK_FLOW.dat</i>         | Filepath for output report containing network flows by commodity.   |
| <i>STANSUM=RCM\output\RAIL_TONKM_VKM_SUM.DAT</i>              | Filepath for output summary report containing tonnes, load and empties for rail by commodity.   |
| <i>TM_EMPTY=EXTRACT\OUTPUT\OD_Emp[fj]_FIN.314</i>             | Filepath for input data for empties used to generate traversal matrices from.   |
| <i>TM_TONNES=EXTRACT\OUTPUT\OD_Tonnes[fj]_FIN.314</i>         | Filepath for input data for tonnes used to generate traversal matrices from.  |
| <i>TM_VHCL=EXTRACT\OUTPUT\OD_Vhcl[fj]_FIN.314</i>             | Filepath for input data for vehicle load used to generate traversal matrices from.  |

|  |  |
|--|--|
| <i>TRAVERSALPATH=TRAVERSA<br/>LFOLDER</i>                | Filepath for traversal matrices.   |
| <i>VEHICLES=201,202,203,204,2<br/>05,206,207,208,209</i> | List of all train types in the ChainChoi output files. The above list is the default, the keyword is needed only if new train types are added. A current list is<br>VEHICLES=201,202,203,204,205,206,207,208,209,210,211,212<br>The number of train types in this parameter is also used to determine the number of train types the program handles, and to allocate variables for this number of train types. |
| <i>VHCLCOSTPATH=Input_CBA\<br/>COST\VHCLS_COMo1.txt</i>  | Path to input file for vehicle costs.  |
| <i>VHCLREP=RCM\Output\VhclR<br/>ep.dat</i>               | Filepath for vhcl report output file.  |
| <i>VISITLINK=ANY</i>                                     | Value that sets whether a link should be checked or not.   |
| <i>VISITNODE=ORDER</i>                                   | Available options: ANY, ALL, ORDER, SINGLE. ANY = any of the given nodes or links must be used. ALL = all of the given nodes and links must be used. ORDER = checks order of nodes. SINGLE = indicates that nodes must be passed in the order given by the NODESSL parameter.  |

## Program structure

The program is originally developed in Eclipse Java IDE. The program has been converted to Netbeans IDE for Samgods 1.2.

### Main classes

#### **SelectDirect.java**

This class holds the java main procedure. It reads the control file and calls a procedure for the requested analysis.

#### **SPT\_Select.java**

Reads and contains data for the spanning tree. Returns the path for a given connection.

### Utility classes

#### **CtlReader.java**

A utility class that reads and holds the values from the control file.

#### **Enums.java**

A utility class that describes array position values.

#### **Funcs.java**

A utility class that has various functions for string handling etc.

#### **Funcs\_CCSlctLink.java**

A utility class that holds functions for empty calculation based on chainchoi input.

#### **Funcs\_CommoditySUM.java**

A utility class that holds functions for creating the data by commodity.

#### **Funcs\_EmptySlctLink.java**

A utility class that holds functions for empty calculation based on selected link input.



### **LgFileReader.java**

A standard FileReader with the additional function that it logs the name of the file read.

### **LgFileWriter.java**

A standard FileWriter with the additional function that it logs the name of the file written.

### **Lists.java**

Lists keeps track of various input data.

## **Changes in SelectDirect 1.2**

### **New features**

Added new report for summarizing empty km and number of vehicles on domestic selectlink-analysis. This report shows km and number of vehicles on and off ferries. This report path can be changed with the VHCLREP parameter.

### **Changes in functionality**

Emptycost is now split between 4 categories: domestic, import, export, transit.

SelectDirect now handles 16 commodities instead of 35. The default value for parameter MAX\_CMD has been changed from 35 to 16.

### **Enhancements**

SelectDirect now handles null references and closing of streams in an improved fashion, preventing memory leakage.

Improved logging to error-files.

## **References**

Henrik Edwards (2015): Railway Capacity Management for Samgods Using Linear Programming

## Appendix – Output data description

This is a description of the Java program SelectDirect output data. The purpose with this text is to describe the output data, thus making the program and data more user-friendly and allow the user to gain a greater understanding. The objective you as a user should have when reading this text is to find out what the tables contain, and which variables are in each output file, an explanatory description and their data type.

The following five output files could be produced<sup>1</sup>:

- LinkSumSL.dat
- ConSumSL.dat
- ChainsSL.dat
- ConnectionsSL.dat
- TotalFlows.dat

### LinkSumSL.dat

Each row relates to a link and vehicle combination. See Table 1.

*Table 1 The LinkSumSL table with information about the variable name, the description and the data type.*

| <b>Variable</b> | <b>Description</b>  | <b>Type</b> |
|-----------------|---|-------------|
| Link            | Index   | Integer     |
| FrVy            | From-node (or start node) in Voyager numbering                            | Integer     |
| ToVy            | To-node (or end node) in Voyager numbering                                | Integer     |
| FrEMME2         | From-node in Emme numbering   | Integer     |
| ToEMME2         | To-node in Emme numbering   | Integer     |
| Vhcl            | Vehicle number, 3 digit format  | Integer     |
| kTon/year       | Link volume in kton per year  | Double      |
| NLoadVhcl/day   | Link flow in number of loaded vehicles per day                            | Double      |
| NEmptyVhcl/day  | Number of empty vehicles per day(derived from LOS-matrices <sup>2</sup> ) | Double      |

### ConSumSL.dat

Each row relates to a connection and vehicle combination. Sums are derived from ConnectionsSL.dat. Please see the description of these variables in ConnectionsSL.dat. Variables Orig and Dest are centroid or terminal nodes. See Table 2.

<sup>1</sup> The exact names of the files are actually handled in a control file, thus dependent on the names given by the keywords in the control file. The names refer to parameters LINKSFILE, CONSUMFILE, CHAINSFILE and CONNECTIONSFILE (TotalFlows.dat hard-coded).

<sup>2</sup> LOS-matrices given by parameter SL\_EMPTY, value found by the key FrEMME2, ToEMME2 and vhcl.

Table 2 The ConSumSL table with information about the variable name, the description and the data type.

| <b>Variable</b>         | <b>Description</b>                                   | <b>Type</b> |
|-------------------------|--|-------------|
| Orig                    | Origin node in Emme numbering                        | Integer     |
| Dest                    | Destination node in Emme numbering                   | Integer     |
| Vhcl                    | Vehicle number, 3 digit format                       | Integer     |
| N_Lvhcls                | OD-connection sum number of loaded vehicles per day  | Double      |
| Tonnes                  | OD-connection sum tonnes per year                    | Double      |
| N_EmptyV(O_D_L)         | Number of empty vehicles (derived from LOS-matrices) | Double      |
| TransportTimeCost_(SEK) | Not implemented                                      | NA          |
| LoadingTimeCost_(SEK)   | Not implemented                                      | NA          |
| InterestCost_(SEK)      | Not implemented                                      | NA          |
| DistCost_(SEK)          | Not implemented                                      | NA          |
| InfraCost_(SEK)         | Not implemented                                      | NA          |
| LoadingCost_(SEK)       | Not implemented                                      | NA          |

### ChainsSL.dat

The table contains the best chain for a given shipment. Variables orig and dest are centroids or terminals. See Table 3.

Table 3 The ChainsSL table with information about the variable name, the description and the data type.

| <b>Variable</b> | <b>Description</b>                       | <b>Type</b> |
|-----------------|--|-------------|
| cmd             | Commodity                                | Integer     |
| key             | Key for a specific shipment <sup>3</sup> | Integer     |
| chaintype       | Chain type                               | String      |
| orig            | Origin node in Emme numbering            | Integer     |
| dest            | Destination node in Emme numbering       | Integer     |

<sup>3</sup> An attempt to describe a shipment: a serial index to the combination P-C-F2Fcategory. The exact definition is found in the documentation concerning the logistic module.

|               |   |        |
|---------------|---|--------|
| Prob          | The probability that the chain is the best chain                    | Double |
| tonnes        | Total volume (tonnes) per year (scaled by probability) <sup>4</sup> | Double |
| TrpCost_(SEK) | Not implemented   | NA     |
| AllCost_(SEK) | Not implemented   | NA     |

### ConnectionsSL.dat

Data is split by commodity. Each value for key consists of one (or multiple) legs, each leg with a submode. Variables orig and dest are centroids or terminals. The variables orig and dest are centroids or terminal nodes. See Table 4.

Table 4 The ConnectionsSL table with information about the variable name, the description and the data type.

| Variable                | Description  | Type    |
|-------------------------|--|---------|
| cmd                     | Commodity (numbers 1-16)                                     | Integer |
| key                     | Key for a specific shipment                                  | Integer |
| leg                     | Order for each leg in the transport chain (1,2,...,5)        | Integer |
| mode                    | Submode  | String  |
| orig                    | Origin node in Emme numbering                                | Integer |
| dest                    | Destination node in Emme numbering                           | Integer |
| vhcl                    | Vehicle number, 3 digit format                               | Integer |
| Prob                    | Probabilty (share) of the demand that use this solution      | Double  |
| N_LVhcls                | Number of loaded vehicles per year (weighted by probability) | Double  |
| tonnes                  | Total volume (tonnes) per year (weighted by probability)     | Double  |
| dist                    | Domestic distance (from ddist LOS matrix)                    | Double  |
| TransportTimeCost_(SEK) | Not implemented  | NA      |
| LoadingTimeCost_(SEK)   | Not implemented  | NA      |
| InterestCost_(SEK)      | Not implemented  | NA      |

<sup>4</sup> From the file given by CCFILES parameter in control file, this is calculated as tonnes = Prob \* NRelations \* AnnualVolume\_(Tonnes).

|                       |                 |    |
|-----------------------|-----------------|----|
| DistCost_(SEK)        | Not implemented | NA |
| InfraCost_(SEK)       | Not implemented | NA |
| LoadingCost_(SEK)     | Not implemented | NA |
| PositioningCost_(SEK) | Not implemented | NA |
| FairwayDues_(SEK)     | Not implemented | NA |
| PilotFees_(SEK)       | Not implemented | NA |
| sel_nodes             | Not implemented | NA |

### TotalFlows.dat

Values are derived from ConnectionsSL.dat. See Table 5.

*Table 5 The TotalFlows table with information about the variable name, the description and the data type.*

| <b>Variable</b> | <b>Description</b>             | <b>Type</b> |
|-----------------|--------------------------------|-------------|
| Vhcl            | Vehicle number, 3 digit format | Integer     |
| N_LVhcls_sumOD  | Not implemented                | NA          |
| Tonnes_sumOD    | Not implemented                | NA          |



Trafikverket, Box 388, 831 25 Östersund. Besöksadress: Kyrkgatan 43 B.  
Telefon: 0771-921 921, Texttelefon: 010-123 99 97

[www.trafikverket.se](http://www.trafikverket.se)